Mozout

Generated on 27/10/2026 21:13

KNOWLEDGE BASE · PUBLIC DOCUMENT

How to create a user with sudo on your VPS and stop logging in as root

VPS & Servers

CODE	VERSION	COUNTRY · LANGUAGE
RLX-INT-KB-4164	v2026.10.10	International · English

MozOut International
RLX Holdings (Pty) Ltd. · Group RLX Holdings
Tax no. (SARS) 943 907 6234 · Registration no. (CIPC) 2025/667953/07

https://www.my.mozout.com/knowledgebase/4164

How to create a user with sudo on your VPS and stop logging in as root

VPS & Servers Created on **October 10, 2026** 3 min read



Root can do anything, so a mistake of yours, or a program's, can wipe everything. The normal practice is to create an **ordinary user** and give it the right to ask for administrator powers only when needed, with the `sudo` command. It takes five minutes and is one of the six basic precautions in **keeping your VPS secure**. The commands are for your own server and run as root; support does not run them for you (see **how far our support goes**).

Step by step

1. **Sign in as root** and create the user. On Ubuntu and Debian: `adduser maria` (it asks for the password and some details, which you can leave blank). On AlmaLinux and Rocky: `useradd -m maria` and then `passwd maria`. Swap "maria" for the name you want, in lower case.

2. **Give it the right to use sudo.** On Ubuntu and Debian: `usermod -aG sudo maria`. On AlmaLinux and Rocky: `usermod -aG wheel maria`. The `-aG` adds to the group without removing from the others: without the `-a` the user would drop out of every other group.

3. **Pass it your SSH key.** If you already sign in to root with a key, copy it, still as root: `mkdir -p /home/maria/.ssh`, `cp /root/.ssh/authorized_keys /home/maria/.ssh/`, `chown -R maria:maria /home/maria/.ssh`, `chmod 700 /home/maria/.ssh` and `chmod 600 /home/maria/.ssh/authorized_keys`. If you do not have a key yet, see **how to create an SSH key**.

4. **Test in a new window, without closing the root one.** `ssh maria@YOUR.VPS.ADDRESS`. Then, once in, `sudo whoami`: it should answer `root`. If it does, the user can do what is needed.

5. **Only then, if you wish, stop root signing in over SSH.** In `/etc/ssh/sshd_config` set `PermitRootLogin no` and restart the service, and test once more in a new window. See also **the SSH key and what to do if it fails**.

I want to…	Command
See a user's groups	`groups maria`
Change their password	`sudo passwd maria`
Lock the password without deleting the account	`sudo passwd -l maria` (sign-in by SSH key stays possible; to cut it, remove the key from the authorized_keys file)
Delete the user and the home folder	`sudo userdel -r maria` (on Debian and Ubuntu also `deluser --remove-home maria`)
Become root from the user	`sudo -i`

Test sudo before you block root.
If the user is not in the right group, `sudo` says it has no permission and you are left with no way to manage the server. Keep the first session open until you confirm sudo works. If you still end up locked out, the route is the console: see **I have lost SSH access to my server**.

One user per person.
Instead of sharing one, create one each, to know who did what and to remove one person's access without affecting the others. Each one's files and permissions are in **Linux file permissions on a VPS**. And never make sudo password-free for everyone out of convenience.

NEED A HAND?

Lost access after changing users or SSH? Tell us what you did and the VPS address.

Open a support ticket →

SEE ALSO

- Your first session on a new Linux VPS →
- How to create an SSH key and log in without a password →
- Keeping your VPS or dedicated server secure: the six that matter →
- Linux file permissions on a VPS: chmod, chown and Permission denied →

Mozout

MozOut International

RLX Holdings (Pty) Ltd. · Group RLX Holdings

TAX NO. (SARS)	943 907 6234
REGISTRATION NO. (CIPC)	2025/667953/07
REGISTERED OFFICE	1111 Olive Street Saint Louis 63101, Missouri, United States
CONTACT	info@mozout.com · +27 78 823 3325 · www.mozout.com
OPENING HOURS	Monday to Friday - 08 AM to 04 PM Saturday & Sunday - Closed

Online version of this document

RLX-INT-KB-4164 · v2026.10.10 · Generated on 27/10/2026 21:13